

Element.ImportData

Overload	Description
<code>ImportData(Object())</code>	Imports the data from a 2-dimensional array into a Table at the point of the current element in the document.
<code>ImportData(Object(), String(), DataImportProperties)</code>	Imports a set of data from an array of column names and a 2-dimensional array of data to a Table created at the point of the current element in the document. Also accepts a DataImportProperties object defining any options for this data import.
<code>ImportData(System.Data.DataTable)</code>	Imports data from a DataTable into a Table at the point of this Element in the document.
<code>ImportData(System.Data.DataTable, DataImportProperties)</code>	Imports data from a DataTable into a Table at the point of this Element in the document. Also accepts a DataImportProperties object that contains the options for importing.
<code>ImportData(System.Data.DataView)</code>	Imports data from a DataView into a Table at the point of this Element in the document.
<code>ImportData(System.Data.DataView, DataImportProperties)</code>	Imports data from a DataView into a Table at the point of this Element in the document. Also accepts a DataImportProperties object that contains the options for importing.
<code>ImportData(Object())</code>	Imports the data from a rectangular array into a Table at the point of the current element in the document.
<code>ImportData(Object(), String(), DataImportProperties)</code>	Imports the data from a rectangular array into a Table at the point of the current element in the document. Also accepts an array of column names and a DataImportProperties object with the import options.
<code>ImportData(System.Data.IDataReader)</code>	Imports the data from a DataReader into a Table at the point of the current element in the document.
<code>ImportData(System.Data.IDataReader, DataImportProperties)</code>	Imports the data from a DataReader into a Table at the point of the current element in the document. Also accepts a DataImportProperties object that contains the import options.

SharePoint Integration Extension Methods

Overload	Description
<code>ImportData(Microsoft.SharePoint.SPList)</code>	Imports the data from a SharePoint List into a Table at the point of the current element in the document.
<code>ImportData(Microsoft.SharePoint.SPView, Microsoft.SharePoint.SPList, DataImportProperties)</code>	Imports the data from a SharePoint View into a Table at the point of the current element in the document. Also accepts a SharePoint List to which the View belongs and a DataImportProperties object with the import options.