

WordTemplate.SetRepeatBlock

Overload	Description
SetRepeatBlock(System.Data.DataSet, String)	Sets the specified repeat block's data source to an ADO.NET DataSet. A repeat block is a fragment in the template document that will be repeated for each row in a data source. In the template document, repeat blocks are defined by Word bookmarks that contain merge fields.
SetRepeatBlock(System.Data.DataSet, String, Int32)	Sets the specified repeat block's data source to an ADO.NET DataSet.
SetRepeatBlock(System.Data.DataTable, String)	Sets the specified repeat block's data source to an ADO.NET DataTable.
SetRepeatBlock(System.Data.DataTable, String, Int32)	Sets the specified repeat block's data source to an ADO.NET DataTable.
SetRepeatBlock(System.Data.IDataReader, String)	Sets the specified repeat block's data source to an IDataReader interface, which may be either a SqlDataReader, OleDbDataReader or an AdomdDataReader.
SetRepeatBlock(System.Data.IDataReader, String, Int32)	Sets the specified repeat block's data source to an IDataReader interface, which may be either a SqlDataReader, OleDbDataReader, or an AdomdDataReader.
SetRepeatBlock(Object(), String(), String)	Sets the specified repeat block's data source to a 1-dimensional array of objects.
SetRepeatBlock(Object(), String(), String)	Sets the specified repeat block's data source to a multidimensional (rectangular) array of objects.
SetRepeatBlock(Object(), String(), String, Int32, Boolean)	Sets the specified repeat block's data source to a multidimensional (rectangular) array of objects.
SetRepeatBlock(Object()(), String(), String)	Sets the specified repeat block's data source to a jagged array (array-of-arrays) of objects.
SetRepeatBlock(Object()(), String(), String, Int32, Boolean)	Sets the specified repeat block's data source to a jagged array (array-of-arrays) of objects.
SetRepeatBlock(System.Collections.IEnumerator, String)	Sets the specified repeat block's data source to an IEnumerator collection.
SetRepeatBlock(System.Collections.IEnumerator, String, String)	Sets the specified repeat block's data source to an IEnumerator collection.
SetRepeatBlock(System.Collections.ICollection, String)	Sets the specified repeat block's data source to an ICollection .
SetRepeatBlock(System.Collections.ICollection, String, String)	Sets the specified repeat block's data source to an ICollection .

SharePoint Integration Extension Methods

Introduced in build 4.5

Overload	Description
SetRepeatBlock(Microsoft.SharePoint.SPList, String, Int32)	Sets the specified repeat block's data source to a SharePoint List.
SetRepeatBlock(Microsoft.SharePoint.SPList, String)	Sets the specified repeat block's data source to a SharePoint List.
SetRepeatBlock(Microsoft.SharePoint.SPView, Microsoft.SharePoint.SPList, String, Int32)	Sets the specified repeat block's data source to a SharePoint View.
SetRepeatBlock(Microsoft.SharePoint.SPView, Microsoft.SharePoint.SPList, String)	Sets the specified repeat block's data source to a SharePoint View.